

## CENTRAL TRANSACTION CODE-RELATED PROFILE CHANGES

### COMPTROLLER OBJECT

Comp. Obj. No.	Screen	Title	Data Elements	Comment
6151	D10	Permit 1200	Effective End Date	Blank Out
6896	D10	Accruals - Expenditure Credit Funding	Effective End Date	Blank Out
6898	D10	Cash Transfer Expend- iture Credit Funding	Effective End Date	Blank Out

### RMDS PRINTING PROBLEMS USING OPTION 1 (NETWORK PRINT)

Users have reported RMDS printing problems when using Option 1 on the SEND REPORT PAGES screen. Some of the reported problems are:

1. Font size changes, and
2. Loss of landscape format

Staff are working on this problem and expect to have it corrected shortly.

In the meantime, if you are experiencing these problems, please change your RMDS Select

Option to **OPTION 2 (BATCH PRINT)** as described on the next page.

When using Option 2 on the Send Report Pages screen, enter 2 after SELECT OPTION, specify PAGE RANGES and press <ENTER> to see the BATCH PRINT OPTIONS screen.

SEND REPORT PAGES							
REPORTNAME . . :RSTARS CONTROL REPORTS							
REPORT TIMESTAMP: 1996-03-22-05.28.29							
SELECTOPTION 2 1.NETWORK PRINT							
2.BATCH PRINT							
3.BATCH TRANSFER							
NETWORK PRINTER ID . .				REQUIRED FOR OPTION 1 ONLY			
SPECIFY PAGE RANGES:							
FROM	TO	FROM	TO	FROM	TO	FROM	TO
1	2						
OPTIONAL HEADER PAGE INFORMATION							
LINE 1 .							
LINE 2 . .							
LINE 3 . .							
LINE 4 . .							
COMMAND ==>							
F1=HELP F3=EXIT							

On the BATCH PRINT OPTIONS screen, the parameters are JOB NAME (User ID followed by a "P") and ACCOUNT (1111). The SYSOUT CLASS will default to "T." Specify a printer ID in the DESTINATION field. Data should not be entered in the WRITER NAME or the FORMS fields. Press <ENTER>. The ADDITIONAL PRINT PARAMETERS screen will appear.

BATCH PRINT OPTIONS	
REPORTNAME ... RSTARS CONTROL REPORTS	
REPORT TIMESTAMP: 1996-03-22-05.28.29	
REQUIRED PARAMETERS:	
JOB NAME ....	#07JHDP
ACCOUNT ....	1111
OPTIONAL PARAMETERS:	
SYSOUT CLASS ..	T
DESTINATION ..	AA05
NAME .....	
TITLE .....	
DEPARTMENT ...	
ROOM .....	
BUILDING ....	
ADDRESS 1 ...	
ADDRESS 2 ...	
ADDRESS 3 ...	
ADDRESS 4 ...	
COMMAND==>	
F1=HELP F3=EXIT F12=CANCEL	

On the ADDITIONAL PRINT PARAMETERS screen, the COPIES field should be entered only when more than one copy is needed. The default value is 1. If you only want one copy, just hit ENTER.

ADDITIONAL PRINT PARAMETERS	
REPORTNAME ... RSTARS CONTROL REPORTS	
REPORT TIMESTAMP: 1996-03-22-05.28.29	
COPIES ...	CHARACTER SET 1 ... FCB ..
PAGEDEF ..	CHARACTER SET 2 ..
FORMDEF ..	CHARACTER SET 3 ..
PRMODE ...	CHARACTER SET 4 ..
CONTROL OPTION .... 1	1. NONE
	2. DEFAULT
	3. USE MEMBER FROM PRINT CONTROL LIBRARY
	4. USER-SUPPLIED PRINT CONTROL
	5. MERGE MEMBER AND USER-SUPPLIED PRINT CONTROL
CONTROL MEMBER NAME ..	REQUIRED FOR OPTION 3; USABLE WITH 5
USER-SUPPLIED CONTROL INFORMATION REQUIRED FOR OPTIONS 4, 5	
LINE 1 ..	
LINE 2 ..	
COMMAND==>	
F1=HELP F3=EXIT F12=CANCEL	

This page last updated 06/18/2001 10:42:00.